



Add a Workstation in Version 6

Assumptions:

- The network is set up and operational.
- The workstation has full read/write access to the server where the PROMAS database will reside.
- PROMAS has been installed on the workstation.
- The PROMAS registration files are on the server.
- You have read the Windows Issues #297 How To PDF document.

PLEASE PERFORM ALL STEPS

A. Check the NetDir setting on an existing workstation.

- Go to C:\Program Files\Borland\Common Files\BDE or C:\Program Files (X86)\Borland\Common Files\BDE.
- Double click on the BDE Administrator icon (bdeadmin.exe)
- Click on the Configuration tab
- Click once on the + sign next to drivers
- Click once on the + sign next to native
- Click once on the circle next to PARADOX
- Note the path in the NetDir field.

B. At the new workstation:

- Go to C:\Program Files\Borland\Common Files\BDE or C:\Program Files (X86)\Borland\Common Files\BDE.
- Right click on the BDEAdmin.exe application file. Select "Run As Administrator"
- Under Object, Options, change the setting to "Win 3.1 and Windows 95/NT compatibility". (That will cause all the settings to be stored in the cfg file instead of some being written to the registry). Click OK.
- Close out of the BDE
- Double click on the BDE Administrator icon (bdeadmin.exe)
- Click on the Configuration tab
- Click once on the + sign next to drivers
- Click once on the + sign next to native
- Click once on the circle next to PARADOX
- Click in Net Dir field under Definition
- Enter whatever was in the NET DIR for the other workstation as noted in Step A.
- Click in Block Size and change it to 32768.
- Click in Level and change it to 4.
- On the left-hand panel click once on the + sign next to System
- Click on the word INIT or on the icon next to it
- Change Local Share to TRUE
- Click in Max Buf Size and change to 8192
- Click in Max File Handles and change to 96
- Click in Memsize and change to 32
- Click in Shared MemSize and change to 8192
- Click on the X in upper right to close
- Click on Yes to save
- Click OK

Directory Controlled by Other .net File

This error message means that the Net Dir field in the BDE is not set up exactly the same way on each workstation. See page 2. Each must match exactly.

C. Net Check Utility

- In Windows, Computer go to your local C drive.
- Go to the \RPROMAS\Bins folder (or APROMAS\Bins for Association program).
- Inside will be a file named NCHECK.exe. Right click and choose Run as Administrator.
- Click on the <Change Registry Settings> button.
- Click <Yes> on the confirm screen
- Click <OK>
- Click on the X in the upper right to close.
- Repeat step B to set User Account Controls back to where it was.

D. Point the working directory to the server.

- At the PROMAS Logon screen click the path above the Database field. That will bring up the Select Working Directory screen.
- Select the server drive.
- Select the RPROMAS (or APROMAS for the Association program) folder.
- Click Save.

E. Logon to PROMAS.

- Select your database from the drop-down list, enter your User Name and Password and click OK.

F. If you have trouble seeing the server in the BDE or the PROMAS Logon screen, turn the User Account Control off:

Windows 7

1. In Windows, open User Accounts by clicking <Start>.
2. Click <Control Panel>, click <User Accounts and Family Safety> (or User Accounts, if connected to a network)
3. Click <User Accounts>.
4. Click <Turn User Account Control on or off>.
5. Unmark the checkbox Use User Account Control to help protect your computer. Click <OK>.

Windows 8

1. Go to File, Explorer
2. Click on System and Security
3. Change User Account control settings.
4. Set to Never Notify.